

Netzwerk konfiguration

/etc/network/interfaces

```
### Hetzner Online GmbH installimage

source /etc/network/interfaces.d/*

auto lo
iface lo inet loopback
iface lo inet6 loopback

auto enp0s31f6
iface enp0s31f6 inet manual

iface enp0s31f6 inet6 static
    address 2a01:4f8:211:1104::2
    netmask 64
    gateway fe80::1

### Proxmox typische Netzwerke
auto vmbr0
iface vmbr0 inet static
    bridge_ports enp0s31f6
    bridge_stp off
    bridge_fd 0
    address 136.243.20.57
    netmask 255.255.255.192
    gateway 136.243.20.1
    pointopoint 136.243.20.1
    up ip route add 136.243.20.34/32 dev vmbr0

### Virtuelle Netzwerke
iface enp0s31f6.90 inet manual
iface enp0s31f6.60 inet manual
iface enp0s31f6.80 inet manual
iface enp0s31f6.40 inet manual

auto vmbr90
iface vmbr90 inet manual
    bridge_ports enp0s31f6.90
    bridge_stp off
    bridge_fd 0

auto vmbr60
```

```
iface vmbr60 inet manual
    bridge_ports enp0s31f6.60
    bridge_stp off
    bridge_fd 0

auto vmbr80
iface vmbr80 inet manual
    bridge_ports enp0s31f6.80
    bridge_stp off
    bridge_fd 0

auto vmbr40
iface vmbr40 inet static
    bridge_ports enp0s31f6.40
    bridge_stp off
    bridge_fd 0
    address 10.6.4.5
    netmask 255.255.255.0
    up route add -net 10.6.32.0 netmask 255.255.255.0 gw 10.6.4.1 dev
vmbr40
    up route add -net 10.6.6.0 netmask 255.255.255.0 gw 10.6.4.1 dev
vmbr40
```

From:
<https://wiki.cooltux.net/> - **TuxNet DokuWiki**

Permanent link:
<https://wiki.cooltux.net/doku.php?id=it-wiki:proxmox:proxmoxserverconfig&rev=1600085006>

Last update: **2020/09/14 12:03**

